



KaozhengPro

IT認證考試題庫 專業平臺

考證寶提供最新考古題與模擬試題
協助您高效通過認證考試

www.kaozhengpro.com

Exam : **922-020**

Title : MCS 5100 Ris.4.0
Installation &
Commissioning

Version : DEMO

1. What is the purpose of the RTP protocol in a Multimedia Communication Server (MCS) 5100 RIs. 4.0 network?

- A. to transport real-time media streams across a packet network
- B. to provide a means of sharing session data between endpoints
- C. to provide a service-enabling protocol for real-time multimedia sessions
- D. to control signaling between the Session Manager and the RTP Media Portal

Answer:A

2. Where is the Unified Network IP Stimulus (UNIStim) protocol used in a Multimedia Communication Server (MCS) 5100 RIs. 4.0 network?

- A. on ISDN PRI connections to the PSTN
- B. between IP Phones and the IP Client Manager (IPCM)
- C. between the Provisioning Client and an external SIP Gateway
- D. between the System Management Console and the Session Manager

Answer: B

3. A customer is deploying a new Multimedia Communication Server (MCS) 5100 RIs. 4.0 system. While editing the installprops.txt file, what IP Address needs to be configured?

- A. the service logical IP address
- B. the floating service IP address
- C. the machine logical IP address
- D. the Dynamic Host Configuration Protocol (DHCP) server IP address

Answer: C

4. The technician is viewing a command typed from a PuTTY terminal that verifies the IP addressing for the System/Accounting Manager. If the interface eth0 is not UP (it is unavailable), to which interface would the machine logically attach itself?

- A. lo0
- B. eth1
- C. dmfe0

D. dmfe0:2

Answer: B

5. A support engineer is preparing to install a Multimedia Communication Server (MCS) 5100 RIs. 4.0 system. The MCS 5100 servers have all been physically installed and cabled to the In-Reach Terminal Server. Which information should you configure on the In-Reach Terminal Server to allow access to the MCS 5100 servers through it?

A. Define the IP address for each MCS 5100 server.

B. Define the IP address for the Management Console PC.

C. Define the port speed for each MCS 5100 server connection.

D. Define the IP Address port number to which the MCS 5100 server is connected.

Answer: C